Setting Up **Apple® iPhone**

1. Turn on your **iPhone** and from the home screen click on **Settings**.

2. From the **Settings** menu select **Mail, Contacts, Calendars**.

3. From the **Accounts** screen select **Add Account**.

Setting Up **Apple® iPhone**

↘ **POP EMAIL ACCOUNT SETUP (cont.)**

**4.** On the **Add Account** page select **Other**.

5. Select **Add Mail Account**.

6. On the **New Account** page, enter your name as you would like it to appear on outgoing messages. Next, enter your username in the form of an email address along with your password. The description can be anything to help you identify this particular email account.

⤡ **POP EMAIL ACCOUNT SETUP (cont.)**

Enter your account information

Cancel   **New Account**   Save

| IMAP | **POP** |

Name	John Smith
Address	John@example.com
Description	My Email Account

Incoming Mail Server

Host Name	pop.emailhosting.com
User Name	John@example.com
Password	●●●●●●●●●●

Outgoing Mail Server

Host Name	smtp.emailhosting.com
User Name	John@example.com
Password	●●●●●●●●●●

7. Select **POP** at the top of your screen.
   - Fill in the **New Account** information.
   - Enter **pop.emailhosting.com** as the incoming mail server and **smtp.emailhosting.com** as the outgoing server.
     Note: The username will be your full email address.
   - Once you're done click on **Save**.

Settings   **Mail, Contacts, Calend...**

Accounts

| John@example.com | › |
| **Add Account...** | › |

| Fetch New Data | Push › |

8. From the home screen select **Settings** -> **Mail, Contacts, Calendars**.
   - Select your mailbox from the list

EMAILHOSTING®

Cancel	Account Info	Done

Address John@example.com

Description My Email Account

Incoming Mail Server

Host Name imap.emailhosting.com

User Name John@example.com

Password ••••••••••

Outgoing Mail Server

SMTP smtp.emailhosting.com ›

Advanced ›

‹ Account Info	SMTP

Primary Server

smtp.emailhosting.com On ›

Other SMTP Servers

Add Server… ›

If Mail is unsuccessful using the primary server, it will try the other SMTP servers in succession.

Cancel	smtp.emailhosting.com	Done

Server ON

Outgoing Mail Server

Host Name smtp.emailhosting.com

User Name John@example.com

Password ••••••••••

Use SSL OFF

Authentication Password ›

Server Port 2500

---

9. On the **Account Info** page select the **SMTP** under **Outgoing Mail Server**.

10. Select **Primary SMTP Server**.

11. Ensure that all of your settings match the above screenshot.
   • **SSL** should be off.
   • **Authentication** should be set to **Password** and the **Server Port** is **2500**.
   • Once complete select **Done**.

↘ **POP EMAIL ACCOUNT SETUP (cont.)**

Cancel	Account Info	Done

Address   John@example.com

Description   My Email Account

Incoming Mail Server

Host Name   pop.emailhosting.com

User Name   John@example.com

Password   •••••••••

Outgoing Mail Server

SMTP   smtp.emailhosting.com ›

Advanced   ›

Account Info	Advanced

Sent Mailbox   ›

Deleted Mailbox   ›

Deleted Messages

Remove   After one week ›

Incoming Settings

Use SSL   OFF

Authentication   Password ›

Delete from server   Never ›

Server Port   110

---

12. Back in the **Account Info** screen select **Advanced**.

13. Specify if and how often you'd like to remove messages downloaded to the device from the server in the **Deleted Messages** field.
Note: When using POP you can download emails and leave a copy on the server, download and delete from the server or download and delete from the server at a later time.
- Set **SSL** to **off**, Set **Authentication** to **Password** and the **Server Port** to **110** and select **Done**.
- Mail setup is now complete.